

11014 MS1

MPLAB® Simulator Fundamentals

© 2007 Microchip Technology Incorporated. All Rights Reserved.

11014 MS1



Class Objective

When you finish this class you will be able to:

- Use MPLAB[®] Simulator to test and debug firmware
- Create and apply simple stimulus

Use Logic Analyzer and Instruction Trace



Agenda

• Understanding MPLAB[®] Simulator

– (demo)

Stimulus

- Asynchronous
- Simple Synchronous
- (Lab 1)

Tools of Simulator

- Stopwatch
- Trace
- Logic Analyzer
- (Lab 2)



MPLAB[®] IDE and Simulator

© 2007 Microchip Technology Incorporated. All Rights Reserved.

11014 MS1



What is MPLAB[®] Simulator?

- One of the MPLAB[®] debuggers
- Supports all PIC[®] MCU & dsPIC[®] DSC families
 - Baseline PIC24
 - Mid-Range __dsPIC30
 - PIC18 -dsPIC33

Speed

. Sophisticated stimulus engine



Why MPLAB[®] Simulator?

• Pure software debugger

- Develop firmware before silicon arrives
- Much faster than using ICD, ICE
- Repeatable testing
 - With pre-set stimulus


Load testingFree!



Block Diagram of Simulator


- Cycle-based CPU simulation
- Registers
 - SFR (WREG, RXREG, T1CON)
 - GPR (2F0h)
- I/O Pins

RA0 (PORTA)U1RX, T0CKI





Alias Names of I/O Pins




© 2007 Microchip Technology Incorporated. All Rights Reserved.



Block Diagram of Simulator


- Simulate behavior of peripherals
 - TIMER
 - UART, CCP, PWM, ADC
 - Input Capture
 - Output Compare
 - Comparator





Functions of Simulator

- Run: until breakpoint is reached
- Halt: stop!
- Step Into 🔁 Out P
- Step Over 📴
- Animate: slow
- Reset: start over





Using Simulator

1. Start MPLAB[®] IDE

<u>Start>Programs>Microchip>MPLAB IDE</u> <u>>MPLAB IDE</u>




2. Select the right device <u>Configure>Select Device...</u>

MPLAB IDE v7.61						
File Edit View Projec	t Debugger	Programmer	Tools	Configure	Window	Help
🗅 🖻 📰 🛛 🐰		🔲 🏄 🤗			evice	
		• • •		Configur	ation Bits.	2
				External	Memory	
				ID Memo	ory	
				Settings		



Select the Right Device

- 3. Choose the Device Family
- 4. Then choose Device
- 5. Tool Support Green: *supported* Yellow: *beta* Red: *not ready*





7.

Simulator

6. Select the Simulator <u>Debugger>Select Tool>MPLAB SIM</u>

t Debugger Programmer Tools Configure Wind	Select Tool	Þ	None
Select Tool 🕨 🗸 None	Clear Memory	•	1 MPLAB ICD 2
Clear Memory 1 MPLAB ICD 2	Run	F9	2 MPLAB ICE 40
2 MDLAD TCE 4000	Animate	1.5	3 MPLAB SIM
3 MPLAB SIM	Halt	F5	4 MPLAB ICE 20
4 MPLAD ICE 2000	Step Into	F7	
	Step Over	F10	
	Step Out		
Simulator	Reset	•	
	Breakpoints	F2	
functions	StopWatch		-
	Complex Breakpoints		
available	Stimulus	•	
available	Profile	•	
	Clear Code Coverage		
	Refresh PM		



Simulator

8.

(Optional) Configure device Configure>Configuration Bits...

Configuration Bits set in code.											
Address	Value	Category	Setting								
300001	27	Oscillator	RC-OSC2 as RA6								
		Osc. Switch Enable	Disabled								
300002	OF	Power Up Timer	Disabled								
		Brown Out Detect	Enabled								
		Brown Out Voltage	2.00								
300003	OF	Watchdog Timer	Enabled N	~							
		Watchdog Postscaler	1:128								
300006	85	Stack Overflow Reset	Enabled								
		Low Voltage Program	Enabled								
300008	OF	Code Protect 00200-01FFF	Disabled								

Changes to configuration effective after next processor reset

Alternatively, set these in code using __config directive



Simulator

9. (Optional) Check Simulator Settings Debugger>Settings...

- Trace Options
- UART I/O
- Animation Speed
- Real time updates
- Break options
- Code Coverage

Simulator Setting	;s		? 🗙									
Code Coverage Osc / Trace Processor Freque	Break Options	0	ts: MHz KHz									
 Hz Trace Options Trace All Break on Trace Buffer Full 32 K lines M lines 												
	OK Cancel Apply											



Demo: Using MPLAB[®] Simulator



Stimulus

© 2007 Microchip Technology Incorporated. All Rights Reserved.

11014 MS1




Stimulus


- A signal to stimulate a device through I/O ports / variables
- Signal can be:
 - UART data (communications)
 - ADC data (temperature sensor)
 - Digital I/O (switches)



Two Kinds of Stimulus









Asynchronous Stimulus

- User-initiated (click a button)
- Any time during simulation

• Apply to:

- I/O pins
- UART buffer registers (RCREG)

Actions:

- Set low / high
- Pulse low / Pulse high
- Toggle



Synchronous Stimulus

- Pre-programmed when to happen
- Applicable to
 - I/O Pins
 - All registers
- Tied to events, e.g.
 - When it is @ cycle 20 or @ 120 ms
 - When PC reaches address 0xC40
 - When ADCBUF is read in program
 - When RA4 is set




Destination of Stimulus

 I/O Pins Toggle pin TOCKI
 Registers

Registers
 UARTRX ← 123
 foo ← 0x5B

 Data Can be injected from data file





Using Stimulus GUI



Using Stimulus

Stimuli are defined in workbook:

- New Workbook
- Open Workbook
- Save Workbook
- Save Workbook As
- Close Workbook


Debugger	Programmer	Tools	Configure	Window H
Select T Clear Me		×) 💣 🖆 [
Run Animate	i	F9		
Halt		F5		
Step Int Step Ov		F7 F10		
Step Ou Reset	t	•		
Breakpo	ints	F2		
StopWa Complex	tch «Breakpoints			
Stimulus		Þ	New Wo	rkbook
Profile		Þ	Open We	orkbook
Clear Co	ode Coverage		Save Wo	orkbook
Refresh	PM			orkbook As
Settings			Close Wo	orkbook



6 Tabs of Stimulus Window

Synchronous

Asynchronous





Steps to Define/Use Stimulus

- 1. Bring up stimulus window Debugger>Stimulus>New Workbook
- 2. **Define stimulus**
- 3. Save stimulus (optional) <u>Debugger>Stimulus>Save Workbook</u>
- 4. Apply stimulus
- 5. Stimulus window remains open
- 6. Start simulation



Asynchronous Stimulus Last tab in Stimulus Window Fire button for each row

Ρ	n /	egister Action	s Advanced Pir	n / Registe	r Cloci	k Stimulus Register Injection Register Trace Async	h
	Fire	Pin / SFR	Action	Width	Units	Comments / Message	
	>	TOCKI	Toggle				
	>	INTO	Set High				
	>	RAO	Pulse Low	2	сус		
	>	RCREG	File Message			message.txt	
	>	RCREG	Direct Message			"Hello World"	

Destination: I/O Pin or RCREG



Asynchronous Stimulus

Pi	Pin / Register Actions Advanced Pin / Register Clock Stimulus Register Injection Register Trace Asynch												
	Fire	Pin / SFR	Action	Width	Units	Comments / Message							
	×	ТОСКІ	Toggle										
	>	INTO	Set High										
	>	RAO	Pulse Low	2	сус								
	>	RCREG	File Message			message.txt							
	>	RCREG	Direct Message			"Hello World"							

Action for I/O Pin: – Set High/Low

- Toggle
- Pulse High/Low for 2 cycles



Asynchronous Stimulus

P	Pin / Register Actions Advanced Pin / Register Clock Stimulus Register Injection Register Trace Asynch												
	Fire	Pin / SFR	Action	Width	Units	Comments / Message							
	×	ТОСКІ	Toggle										
	>	INTO	Set High										
	>	RAO	Pulse Low	2	сус								
	>	RCREG	File Message			message.txt							
	>	RCREG	Direct Message			"Hello World"							

Action for RCREG:

Message-based Stimulus

- File Message: Inject from file
- Direct Message: defined in GUI

More information in appendix



Asynchronous Summary

- Quick stimulus to test application
- Possible uses:
 - True random event (user key press)
 - Asynchronous UART message

Onto Synchronous Stimulus...



Pin/Register Actions

Define Sequence of stimulus @ pre-set time

- Pin T0CKI, RB0
- PortPORTA
- SFR TMR2, WREG

Bit field
 SSPBUF

	Stimu	ulus	- [Unti	tled]						
	Pin / F	egiste	er Action	IS Adv	vanced Pir	1 / Reaist	ter Clock	Stimulus Register I	njection Register Trace /	Asynch
	Tim	ne Uni	ts cyc	×		F	lepeat 📃	after: 1 (de	at:	ec)
	Ti	me	TOCKI	RBO	PORTA	TMR2	WREG	SSPBUF.SSPBUF	Click here to Add Signals	^
	(de	ec)	(bin)	(bin)	(hex)	(hex)	(hex)	(bin)		
	<u> </u>	10		1	1E		80	0000001		
		12	1					01010100		
		15	0		20	A0	D8			
		20		0		BF		00011111		
		30	1				2C	00011111		
			F	10	nto	: 21	tr	cle 1	0 12	
					110				<i>, , , , , , , , , , , , , , , , , , , </i>	_
			16		20	21) -1	fter re	cot	
			10), 4	20,	JU	<i>i</i> ai	ler re	Sel	×
_							_			
Ľ	Advan	ced		Apply	B	emove	Delete	e Row Save	Exit I	Help

© 2007 Microchip Technology Incorporated. All Rights Reserved.



Pin/Register Actions

• Time Unit

- common to all events on this tab
- Cycle
- Hour:Min:Sec
- ms
- US
- ns


Stimulus - [Untitled]												
Pi	in / Regist	er A	ctions	کم Adv	vanced Pir	n / Regis	ter	Clock :				
	Time Un	its	сус	~			lepe	at 📃 a				
	Time	ТО	cyc h:m:		Instruction Cycles Hours:Minutes:Seconds							
	(dec)	(b	ms		econds _			ex)				
	10		us Ns		microseconds nanoseconds							
	12		1	11-211-	500001100							
	15		0		2C	AO		D8				
	20			0		BF						



Pin/Register Actions

Add/Remove Signals


Signal Filter:





What Happens at Run Time?

- At cycle 10:
 - RB0 ← high
 - PORTA ← 1E
- At cycle 12:
 - T0CKI ← high
- At cycle 15:
 - − T0CKI \leftarrow low
 - PORTA \leftarrow 2C
 - TMR2 ← A0



Radix for data entry




Might need to repeat stimuli

Check "Repeat" and enter delay

10 12 15 20 30

10 12 15 20 30

[wait 20 cycles]



10 12 15 20

50 **60 62 65 70 80**...

30


© 2007 Microchip Technology Incorporated. All Rights Reserved.



"Restart at" option

Selects which row to begin repeating after delay

10 12 15 20 30





Pin/Register Summary

- Set / Clear pin, SFR, SFR bit field
- At specific time during simulation
- All data contained in the workbook
- Possible uses:
 - Setting two IRQ flags simultaneously
 - Simulating A/D buffer (ADRES)
 - Setting pulse to ext clock input T0CKI
 - Duration test (using "repeat")



Lab 1: Simple Stimulus

C:>Masters>11014>Lab1>Lab1.mcw

© 2007 Microchip Technology Incorporated. All Rights Reserved.

11014 MS1



Other Stimulus Tabs

Register Injection

- Attach input data file to Register or GPR
- Register Trace
 - Attach output file to Register or GPR

Clock Stimulus

Generates waveform to I/O pin



Other Stimulus Tabs (Cont'd)

Advanced Pin/Register

Conditional Pin/Register stimulus

• Other MASTERS classes


- Advanced Stimulus (11015 MS2)
- Debugging Techniques (11016 MS3) NEW!



Tools in Simulator




Tools in Simulator





Tools in Simulator



Profile


 Count # of times used by each instruction

Real-time Watch Window

- See contents of memory / variables during simulation
- Drag and drop variables from editor




Execution Trace



- Record <u>execution history</u> of program
- Instruction tagged with time stamp (execution cycle)
- Disassembled Opcodes
- Source and Destination Data values
- Source and Destination Address



Execution Trace (cont'd)



- Filter In/Out from source
- Trace to Source Correlation
- Select Menu
 <u>View>Simulator Trace</u>
- Trace All must be selected in debugger settings
- Trace buffer up to 2GB (one trace record ~40 bytes)



Trace to Source Correlation


• Right click \rightarrow select Show Source

Line	Addr	Op Labe	1	Inst	ructi	on	SA	SD	DA	DD	Cycl	les
0		E07	MOVI	W 0x7			W		W	07	0000000	
1		EC1		F Oxfc	1. AC	CESS			OFC1	07	0000000	
2		AD5				ACCESS	0FD5	FF	0FD5	FF	0000000	1.1.1.1.1.1
3	0006 8	12122 20			and the state of the state	ACCESS		FF	0FD5	FF	0000000	
4	0008 8	CD5				ACCESS		FF	OFD5	FF	0000000	0000
				an a					Close	e		122000
C:\MAS ⁻ 10		114\LAB1\L ude p18f	· · · · · · · · · · · · · · · · · · ·		; :	standard	heade	r fo	Go T	- ·	ie N	
											2	
11 12			0x7			configure			Relo	8014	N	
12 1 14 16		movwf bsf T bsf T bsf T	ADCON OCON, 1 OCON, 1 OCON, 1	rocs rose	; ; ; ; ; ; ; ;	for digit use exter increment TMRO as (tal RA nal s t TMRO 3-bit	0 in ourc on	Rese Displ Clear	et Time ay Time r Trace	Stamp e Buffer sassembly	
11 12 1 15 16 17 18 19	;	movwf bsf T bsf T bsf T clrf	ADCON OCON, 1 OCON, 1	FOCS FOSE FO8BIT	; ; ; ; ; ; ; ; ; ;	for digit use exter increment	tal RA cnal s t TMRO 3-bit RO	0 in ourc on	Rese Displ Clear Symb	et Time ay Time r Trace bolic Dis bolic Dis	e Buffer sassembly	



Filter Trace – selective

Trace certain
 Ines, e.g. loop
 right click→
 Add Filter-in Trace




Not trace some
 e.g. eliminate
 wait loops
 right click→
 Add Filter-out Trace

C:\MPLABnet\Docs\MSTRS\2005\LAB_908\LAB9									
1 70	SAMPLE_ADC_CHAN	15							
1 71 🛛	bsf	ADCONO, CHSO							
1 72 🛛	bcf	ADCONO, CHS1							
1 73 🛛	bsf	ADCONO, CHS2							
174 🛛	movlw	LOW SAMPLE_AP							
1 75 🛛	movwf	SAMPLE_ARRAY							
1 76	movwf	FSR							




Code Coverage





Stopwatch




Measures in cycles & time
 Reset to zero upon reset

	Stopwatch	Total Simulated
Synch Instruction	Cycles 75	7
Zero Time (uS	ecs) 15.000000	15.00000
Processor Frequency	(MHz)	20.00000




Breakpoint





Complex Breakpoints






A then B must happen in order

Logic

Analyzer




Logic Analyzer



- Display I/O port data graphically
- Uses data in trace buffer
- Trace MUST be enabled (Trace All selected in settings)
- Max. 32 channels
- Bus (collection of I/O pins) e.g. PORTB = RB0...RB7



Logic Analyzer (Cont'd)




- Simple Trigger on a PC
 - <u>Start</u>: history after trigger
 - <u>End</u>: history before trigger
 - <u>Center</u>: history before and after trigger
- May stop at trace buffer full
- Cursors for time measurement

Printable displays



Logic Analyzer (Cont'd)

- View>Simulator Logic Analyzer
- Simple Trigger Definition






Lab 2: Logic Analyzer

<u>C:>Masters>11014>Lab2>Lab2.mcw</u>



Summary





Summary

MPLAB[®] IDE and Simulator

Stimulus

- Asynchronous
- Simple Synchronous
- Tools in Simulator
 - Trace
 - Logic Analyzer



Where to find out more

• MPLAB[®] IDE Help

- Topic: MPLAB SIM
- Forums / Webinars

<u>http://forum.microchip.com</u>

<u>http://techtrain.microchip.com/webseminars</u>



Useful Links


- Microchip Change Notification (good way to keep up to date on latest MPLAB[®] IDE and C18/C30 releases, as well as important Dev Tool notifications);
- http://cn.microchip.com/sales/product change.nsf
- Microchip Dev Tools Getting Started (series of many tutorials and overviews):
- http://www.microchip.com/stellent/idcplg?ldcService=SS GET PAGE&nodeld =2122
- **Microchip archives:**
- http://www.microchip.com/stellent/idcplg?ldcService=SS GET PAGE&nodeld =1406&dDocName=en023073
- Development Tool Selector (to find out tool support, accessories, adapteres, etc.):
- http://www.microchip.com/stellent/idcplg?ldcService=SS GET PAGE&nodeld =1496
- Third Party Development Tools:
- http://www.microchip.com/stellent/idcplg?ldcService=SS GET PAGE&nodeld =1926&type=-1&label=A
- **MPLAB** download page:



THANK YOU!



Block Diagram of Simulator





Inject values from data file

Stimulus - D:\...\Lab1.sbs

in / Register Actions Advanced Pin / Register Clock Stimulus Register Injection Register Trace Asynch									
Reg / Var	Trigger	PC Value	Width	Data Filename	Wrap	Format	Comments		
PORTA	PC =	foo	1	porta_input.txt	Yes	Hex	(optional)		
ADRESL	Demand		1	adc_input.txt	No	Dec	(optional)		
RCREG	Message		1	uart_input.txt	Yes	Pkt	(optional)		
	Reg / Var PORTA ADRESL	Reg / VarTriggerPORTAPC =ADRESLDemand	Reg / VarTriggerPC ValuePORTAPC =fooADRESLDemand	Reg / VarTriggerPC ValueWidthPORTAPC =foo1ADRESLDemand1	Reg / Var Trigger PC Value Width Data Filename PORTA PC = foo 1 porta_input.txt ADRESL Demand 1 adc_input.txt	Reg / Var Trigger PC Value Width Data Filename Wrap PORTA PC = foo 1 porta_input.txt Yes ADRESL Demand 1 adc_input.txt No	Reg / Var Trigger PC Value Width Data Filename Wrap Format PORTA PC = foo 1 porta_input.txt Yes Hex ADRESL Demand 1 adc_input.txt No Dec		

Can inject a message to UART Select Trigger = Message Can inject to GPR (variable) also



Reg / Var	Trigger	PC Value	Width	Data Filename	Wrap	Format
PORTA	PC =	foo	1	porta_input.txt	Yes	Hex
ADRESL	Demand		1	adc_input.txt	No	Dec
RCREG	Message		1	uart_input.txt	Yes	Pkt

Destination

- SFR (e.g. ADRESL, RCREG), or
- GPR (aka. Variable)
 - Select variable from drop down
 - Type address directly (2C0) in hex



Reg / Var	Trigger	PC Value	Width	Data Filename	Wrap	Format
PORTA	PC =	foo	1	porta_input.txt	Yes	Hex
ADRESL	Demand		1	adc_input.txt	No	Dec
RCREG	Message		1	uart_input.txt	Yes	Pkt

- Trigger
 - PC=

when PC reaches a location, e.g. foo

- On Demand

when the program reads register/variable

Message (UART only) data injected to RCREG per baud rate



Reg / Var	Trigger	PC Value	Width	Data Filename	Wrap	Format
PORTA	PC =	foc	1	porta_input.txt	Yes	Hex
ADRESL	Demand		1	adc_input.txt	No	Dec
RCREG	Message		1	uart_input.txt	Yes	Pkt

- Width (bytes)
 - SFR (dsPIC[®] DSC: 2, others: 1)
 - GPR (user-specified)
- Wrap

- Wrap-around at the end of input file



Register Injection Summary

Difference than Pin/Reg Actions Tab

- Data is not defined in the workbook
- Use Excel-generated data
- Can switch test data set easily

Possible uses:

- A/D simulation (ADRES)
- Zero-crossing covered in
 Advanced Stimulus (11015 MS2)



Register Trace

Stimulus - D:\\Lab1.sbs										
Pin / Register Actions Advanced Pin / Register Clock Stimulus Register Injection Register Trace Asynch										
	Label	Reg / Var	Trigger	PC Value	Width	Trace Filename	Format	Comments		
	(optional)	PORTC	Demand		1	portc_output.txt	Hex	(optional)		
	(optional)	WREG	PC =	incw	1	wreg_input.txt	Hex	(optional)		

- Similar to Register Injection Tab
- Sends register value to output file
- Supports GPR / variable

No Wrap column



Register Trace

	Reg / Var	Trigger	PC Value	Width	Trace Filename	Format					
	PORTC	Demand		1	portc_output.txt	Hex					
	WREG	PC =	incw	1	wreg_input.txt	Hex					
D	Demand										

- Every time the program changes the register/variable
- PC=
 - Every time PC reaches a location
 - e.g. label *incw* or address 2C0



Register Data File Formats

Format

- Hex: white space
 delimited hex value
 e.g. 1FF AC 53
- Dec: white space
 delimited dec value
 e.g. 128 75 145
- Raw: binary data recorded as-is

- Packet: only for UART buffer
 - Combo of Hex and "string"
 - Wait time

wait 2 ms 61 62 62 20 "abc"



Clock Stimulus

Generates waveform to pin

Target Pin Stimulus D:\...\Lab1.sbs Initial State Pin / Regist, Actions Advanced Pin / Register Clock Stimulus Register Injection Register Trace Asynch Low Cycles High Cycles Lab Pin Initial End Comments ~ Begin Low Cycles At Start Never High 10 RC4 is High T1CKI Never 20 23 сус CCP1 200 cyc+ Low High Cycles At Start PC = foo Begin End Begin cond. At Start Never O PC hex/label O PC = foo hex/label = Cycle = dec absolute time 🔵 Cycle 😑 dec from clock start End cond. O Pin ⊇Pin = RC4 🗸 is 🛛 High 🗸 is Advanced.. Save Workbook Exit Help Apply Delete Row



Clock Stimulus

Any type of clocking signals Possible uses:

- TMR external clock signals T0CKI
- Key bounce covered in
 Advanced Stimulus (11015 MS2)




Advanced Pin/Register

- Pin/Register assignment with <u>conditional</u> control
- Condition

-If TMR2 is E0 -If INT1IF is '1'

- Assignment
 - -Triggered once
 - -Whenever cond happens





Advanced Pin/Register

Provides flexibility with gating

 Complex pin and register stimulus based on other signals

Possible uses:

 Set IRQ flags based on clock stimulus

Pulse train – covered in Advanced Stimulus (12025 MS2)



11014 MS1

MPLAB Simulator Fundamentals

(END)

© 2007 Microchip Technology Incorporated. All Rights Reserved.

11014 MS1



Trademarks

The Microchip name and logo, the Microchip logo, Accuron, dsPIC, KeeLoq, KeeLoq logo, microID, MPLAB, PIC, PICmicro, PICSTART, PRO MATE, rfPIC and SmartShunt are registered trademarks of Microchip Technology Incorporated in the U.S.A. and other countries.

AmpLab, FilterLab, Linear Active Thermistor, Migratable Memory, MXDEV, MXLAB, SEEVAL, SmartSensor and The Embedded Control Solutions Company are registered trademarks of Microchip Technology Incorporated in the U.S.A.

Analog-for-the-Digital Age, Application Maestro, CodeGuard, dsPICDEM, dsPICDEM.net, dsPICworks, ECAN, ECONOMONITOR, FanSense, FlexROM, fuzzyLAB, In-Circuit Serial Programming, ICSP, ICEPIC, Mindi, MiWi, MPASM, MPLAB Certified Iogo, MPLIB, MPLINK, PICkit, PICDEM, PICDEM.net, PICLAB, PICtail, PowerCal, PowerInfo, PowerMate, PowerTool, REAL ICE, rfLAB, Select Mode, Smart Serial, SmartTel, Total Endurance, UNI/O, WiperLock and ZENA are trademarks of Microchip Technology Incorporated in the U.S.A. and other countries.

SQTP is a service mark of Microchip Technology Incorporated in the U.S.A. All other trademarks mentioned herein are property of their respective companies.